

body

2025/12/06 06:15 i body

2025/12/06 06:15 ii body

Table of Contents

bodyi

2025/12/06 06:15 iii body

2025/12/06 06:15 iv body

Click **+Add** to add a row.

Extra Duty Code Click down have Not The job of the contract of	te: All distributions for a particular job code and account type are totaled gether. Any new type G distributions are totaled with the regular type G tributions. The total contract amount is applied to these distributions. The two-digit code of the additional job assignment. The drop who can include type G and type S extra duty codes. If the employee does not we any extra duties entered on the Pay Info tab, no codes are displayed. The type G extra duty code can be split between account codes. The extra duty code cannot be split between job codes. It can only exist with one job code.
Extra Duty Code Click down have Not The job of the contract of	tributions. The total contract amount is applied to these distributions. tk ✓ to select the two-digit code of the additional job assignment. The drop wn can include type G and type S extra duty codes. If the employee does not we any extra duties entered on the Pay Info tab, no codes are displayed. tes: type G extra duty code can be split between account codes. The extra duty code cannot be split between job codes. It can only exist with one job code.
Not The	wn can include type G and type S extra duty codes. If the employee does not we any extra duties entered on the Pay Info tab, no codes are displayed. tes: e type G extra duty code can be split between account codes. The extra duty code cannot be split between job codes. It can only exist with one job code.
The job	e type G extra duty code can be split between account codes. The extra duty code cannot be split between job codes. It can only exist with one job code.
job (code cannot be split between job codes. It can only exist with one job code.
The	
	e type S extra duty code can only have an XTRA job code.
Account Type Click	ck ullet to select the one-digit code of the account type for that job.
1	count Type B (Non-TRS taxable business allow) is used when the Tax column s been completed under Business Allowance on the Pay Info tab.
1	count Type G (Standard gross pay) represents the contract amount from the Info tab.
1	count Type T (Non-TRS non-taxable business allow) is used when the Non Tax umn has been completed under Business Allowance on the Pay Info tab.
exp	count Type X (TRS 373 distr contrib) is used when the above state base bense is to be posted to an account other than the one chosen for the type G count.
Not toge	te : All distributions for a particular job code and account type are totaled jether. Any new type G distributions are totaled with the regular type G tributions.
from Acc exp	to select the code which identifies the account m which funds are expended for the activity code. For extra duty accounts, the count Code field is populated from the extra duty code table. Only benditure accounts with object code 6XXX are allowed.
valid the	te : When the user is logged on to the current payroll files, the account code idation occurs against the Finance Chart of Accounts. If the user is logged on to enext year payroll files, the account code must exist in the Budget > intenance > Budget Data tables.
	plays the description associated with the budget code.

2025/12/06 06:15 1 body

Field	Description
Amount	Type the dollar value to be expended from the budget code. Type all or part of the contract total from the Job Info tab. If the Distributions Built By Amt or % field on the District HR Options page is set to <i>Percentage</i> , then only the Percentage field is enabled for use. For a salaried (pay type 1 or 2) employee, the data in this field is used to calculate the percent amount. Notes :
	For extra duty accounts, the maximum amount that can be entered must match the amount that the extra duty codes have defined on the Pay Info tab. This applies even if the amounts are distributed among several accounts.
	Even if the distributions are entered by percent, the amount is always entered for these distributions.
Percent	Type what percentage of the total pay rate is represented by the amount indicated. The percentage is the portion of contract total from the Job Info tab. If the Distributions Built By Amt or % field on the District HR Options page is set to <i>Amount</i> , then only the Amount field is enabled for use. This field is calculated by the system for salaried (pay type codes 1 and 2) employees. For hourly (pay type 3) employees, the user enters data into this field.
	For each job that is not XTRA, the account type percent total must equal 100% (e.g., if an employee has a job that is not XTRA, the type G percents for that job must total 100%, the type B percents for that job must total 100%, and the type T percents for that job must total 100%). For each job that is XTRA, the account percents for each extra duty code must
	total 100%.
Activity Code	Click to select the two-digit code identifying the activity for which the employee is receiving pay according to the budget code and amount indicated. This code is required for PEIMS purposes. For extra duty accounts, the Activity Code field is populated from the extra duty job code table.
TRS Grant Code	This field is populated automatically for active employees based on the grant code associated to the fund as defined on the Tables > Salaries > Fund to Grant tab.
Worker's Comp Code	Click to select the workers' compensation code (e.g., A, B), or leave blank if the distribution is not subject to workers' compensation taxes. This field is only enabled if the Extra Duty Code field is populated.

2025/12/06 06:15 2 body

Field	Description
Expense 373	Click to select if the account should be used in the ASB distribution for TRS. If N (<i>Account not used in ASB distribution</i>) is selected, it is not used for distribution of the above state base amount on the TRS 373 Report. For extra duty accounts, the Expense 373 field is populated from the Extra Duty Job Code table. Notes :
	For type S distributions, if Y (<i>Account used in ASB distribution</i>) is selected, it is included in the Gross field on the Maintenance > TRS YTD Data page under TRS Deposit Information and is not included in the Suppl Salary field. It is included in the calculation and distribution in the adjusted TRS salary on the TRS 373 Report (HRS4000). If N (Account not used in ASB distribution), it is included in the Gross and Suppl Salary fields on the Maintenance > TRS YTD Data page under TRS Deposit Information; however, it is not included in the adjusted TRS salary on the TRS 373 Report or on the distribution report.
	For type S extra duty jobs, if N (Account not used in ASB distribution), the amounts are not included in the calculation or distribution in the adjusted TRS salary on the TRS 373 Report.
Employer Contribution	Select if the distribution should be included as an employer insurance contribution. The field is only available when account type G is selected.
Performance Pay	Select if the amount to be paid for this account should be included in the TRS deposits performance pay calculations. The field is only available for account types G or S.

Click **Re-sort**. The records on the tab are sorted by job code, account type, and extra duty code.

Click **Refresh Percentages** or **Refresh Amounts** to update the percentage or amount totals if new percentages or amounts are added.

Click **Save**.

2025/12/06 06:15 3 body