

# **Admin - Alert Settings**

### **Table of Contents**

Admin ·	· District Configurable		1
---------	-------------------------	--	---

# Admin - District Configurable

#### ASCENDER ParentPortal Admin > Admin Settings > District Configurable

This page is only available to users who log on to ASCENDER ParentPortal with a district-level administrator account.

This page allows you to set a district-level schedule for the parent alert messages, as well as several district-level security settings.

**Alerts** refers to the update that occurs in the system.

**NOTE**: Please contact your System Administrator if your district wants Alerts turned off.

**Notification** refers to the text or email message that is set to the parent as notification that there is an alert. Notifications do not have to go out at the same time the alert occurs.

#### **Set Alerts**

Set Alerts			
Start Time:	End Time:	Interval:	
8:00	▼ 18:00	▼ 1 Mins Save	

Start/End Time	Select the start and end times to specify the time of day when alerts are generated.
	Type the number of minutes that will elapse between each alert during the specified time.

1

Click Save.

#### **Set Notifications**

Set Notifications			
Start Time: 8:00	End Time:	▼ 1 Mins Save	

Start/End Time Select the start and end times to specify the time of day when notifications are ser	
	to parents.
Interval Type the number of minutes that will elapse between each notification du specified time.	

#### Click Save.

### ParentPortal Settings

ParentPortal Settings	
ParentPortal Default URL: 🕜	
Email Settings	
Use Authenticated Email Server: 🚱	Yes
Mail Server Host: 🚱	
Mail Server Port: 😧	
Mail Server From: 😮	
Maximum Number of Emails: 📀	
Mail Server Login: 🚱	
Mail Server Password: 🔞	
Use Encryption: 🕜	
SMS Settings	
SMS Default URL: 🔞	
Save	

ParentPortal Default	Type the full URL that parents in the district will use to access ASCENDER	
URL	ParentPortal. This URL will be used during the email verification process.	

### Under Email Settings:

User Authenticated Email Server	Indicate if the client's email notification email server requires a login and password. If <b>Yes</b> , enter the user name and password in the <b>Mail</b> <b>Server Login</b> and <b>Mail Server Password</b> fields.	
Mail Server HostIndicate the address of the outgoing mail server.		
Mail Server PortSet the port that the alert service will be running on.		
Mail Server From	Type the email address that will be displayed in the From field when a message is sent by the ParentPortal mail server.	
Maximum Number of Emails	Type the maximum number of email messages that go out in a notification run.	
Mail Server Login	If using an authenticated email server, type the user name.	
Mail Server Password	If using an authenticated email server, type the password.	
Use Encryption	Select to use encryption.	

□ Under SMS Settings:

**SMS Default URL** Type the path used for text messages.

Click Save.

#### Email Authentication Verification

Email Authentication Verification		
Email Address:		
Send		


**Email Address** Type any email address you wish to test. This allows you to confirm that SMTP and other settings are set up correctly.


Click Send.

If the email address is set up correctly, a message will be delivered to that email address indicating that it was verified and functioning properly.

4

PP





## **Back Cover**